Semesent WORKING WITH POINT CLOUDS - GCP WORKFLOW

DOCUMENT NUMBER: INSTR-033 REVISION NUMBER: 1.0 RELEASE DATE: 19 DEC 2024

PREPARED BY: Emesent PTY LTD Level G, Building 4, Kings Row Office Park 40-52 McDougall ST, Milton, QLD, 4064 Australia

EMAIL: CUSTOMER-SUCCESS@EMESENT.IO PHONE: +617 3548 9494

Copyright

The content of this document is confidential and intended for reading only by the addressee. All rights including Intellectual Property Rights flowing from, incidental to or contained in this document irrevocably vest in Emesent unless otherwise agreed to in writing.

©Emesent 2024

Using this manual

Hovermap is a powerful system that can be used as a Lidar mapping payload but also as an advanced autopilot for drones. It is therefore recommended to read the user manual thoroughly to make use of all its capabilities in a safe and productive way.

Disclaimer and safety guidelines

This product is not a toy and must not be used by any person under the age of 18. It must be operated with caution, common sense, and in accordance with the instructions in the user manual. Failure to operate it in a safe and responsible manner could result in product loss or injury.

By using this product, you hereby agree that you are solely responsible for your own conduct while using it, and for any consequences thereof. You also agree to use this product only for purposes that are in accordance with all applicable laws, rules and regulations.

The use of Remotely Piloted Aircraft Systems (RPAS) may result in serious injury, death, or property damage if operated without proper training and due care. Before using an RPAS, you must ensure that you are suitably qualified, have received all necessary training, and read all relevant instructions, including the user manual. When using an RPAS, you must adopt safe practices and procedures at all times.

Warnings

- This document is legally privileged, confidential under applicable law and is intended only for the use of the individual or entity to whom it is addressed. If you have received this transmission in error, you are hereby notified that any use, dissemination, distribution or reproduction is strictly prohibited. If you are not the intended recipient, please notify the sender and delete the message from your system.
- Always be aware of moving objects that may cause serious injury, such as spinning propellers or other components. *Never* approach a drone while the propellers are spinning or attempt to catch an airborne drone.



Class 1 Laser Product (21 CFR 1040.10 and 1040.11)

WARNING HAZARDOUS MOVING PARTS KEEP FINGERS AND OTHER BODY PARTS AWAY



Contents

1.	Introduction1
2.	The GCP workflow2
3.	Prepare your GCP targets
4.	Capture your data4
5.	Save the survey data4
6.	Configure your georeferencing job7
7.	Start processing 10
8.	Review Aura's constellation matching11
9.	Adjust the point cloud 14
10.	Match targets to the correct landmark 15
11.	Save the constellation file
12.	Finish processing 19
13.	View the final output

1. Introduction

The best way to improve the quality of your scan data is by georeferencing your scans using Emesent's Ground Control Points (GCPs) – bright white reflective targets that Hovermap can easily see.

GCPs can enable new scanning opportunities and use cases, including long, large, and feature-poor assets such as roads, stadiums, and tunnels, which were previously a challenge for SLAM-based mapping.


The GCP feature can:

- enhance Hovermap SLAM-based mapping capabilities
- improve scan accuracy by removing drift
- position your scan in the real world
- increase point cloud accuracy
- detect distortions in your point cloud


This document will guide you through the steps in the GCP workflow required to georeference your scan.

2. The GCP workflow

The GCP workflow is part of the overall scan processing workflow. At the constellation matching stage, Emesent Aura will try to automatically align the survey points. If it can't do this, you will have the option to do a manual alignment, before resuming processing.



Once you have prepared your GCP targets, the basic process for GCP processing is as follows.



3. Prepare your GCP targets

Depending on your requirements for the scan, we recommend that you capture several GCPs. Ideally, they will surround your area of interest.

Follow this process for the best results:

- 1. Select a target size to suit the capture method: the 250mm-diameter target is better for drone scans, the smaller 150mm-diameter target is better for walking or Backpack scans.
- 2. Install at least three targets. The height is not important. The more targets you use, the more accuracy and redundancy you'll have.
- 3. Consider how you distribute the targets. Try to install them at regular intervals around the extent of the project, approx. every 40m, so you don't accumulate too much drift. In feature-rich environments you can space them further apart (about 50m), or closer together in feature-poor environments (every 10m).
- 4. If possible, securely screw or glue your targets in place so that they don't move during your scan.
- 5. When placing your GCPs, orientate them to reflect the scanning beam at less than a 30 degree angle from the perpendicular back to the Hovermap. So for drone scans, the GCPs should be placed horizontally in your capture area; for walking or vehicle scans, the GCPs should be placed perpendicular to your direction of travel.
- 6. Before you start scanning, survey-in the center of each target.

0

4. Capture your data

- 1. Perform a continuous scan that captures all the GCPs and the project area.
- 2. While scanning, spend a bit more time near each target so that they show up clearly in the point cloud, but stay at least 1.5m away from the target. It's even better if you can scan near to each target multiple times during the scan (for example, at the start and end of a stope scan) walk around the target as you point the Hovermap at it.

It's better to spend more time in the field scanning your project than trying to fix the scan during processing.

5. Save the survey data

 Save the survey data as a [yourfilename].csv file using the format described below. The format of the CSV file should be as follows: Landmark ID, Longitude (in Eastings), Latitude (in Northings), Height (in metres), and Target Radius (in metres). It is not necessary to include the column headers when loading the CSV file into Aura. However, the number and order of the columns should be maintained as shown in the example below. Ensure that the survey data has exactly 5 columns. as shown below:

S001,500682.435,6961357.168,11.582,0.125 S002,500684.698,6961354.205,11.517,0.125 S003,500689.328,6961351.237,10.998,0.125 S004,500694.064,6961349.341,10.503,0.125 S005,500699.049,6961348.999,9.855,0.125 S006,500703.646,6961350.846,9.414,0.125



• The importer will ignore the first line if header strings are detected.

id,x,y,z,radius

S001,500682.435,6961357.168,11.582,0.125 S002,500684.698,6961354.205,11.517,0.125 S003,500689.328,6961351.237,10.998,0.125 S004,500694.064,6961349.341,10.503,0.125 S005,500699.049,6961348.999,9.855,0.125 S006,500703.646,6961350.846,9.414,0.125

The data must be supplied using the right-handed coordinate system (i.e. the elevation 'z' is up).

Creating your survey information in a CSV file using a spreadsheet might look like this:

Table 1Survey Data Format

8

ID	х	Y	Z	Radius
S001	500682.4	6961357	11.582	0.125
S002	500684.7	6961354	11.517	0.125
S003	500689.3	6961351	10.998	0.125

The GCP dataset is not part of the point cloud but is *associated* with it. The structure of the dataset is as follows:

- There is only one constellation, but each constellation can have multiple landmarks.
- Each of these landmarks can have multiple targets assigned to them.

For definitions of these concepts, refer to the Emesent Aura Glossary section.





Figure 1 GCP Dataset Structure

6. Configure your georeferencing job

- 1. Open Emesent Aura. Make sure you have an active **GCP** license.
- 2. In the **Process** tab, click **Process Scan**.
- 3. In the **Configure New Scan Job** panel, select the **GCP** workflow then click **Add GCP Data**.



- 4. In the dialog box that displays, click **Add Scan Data**.
- 5. Browse for the folder that contains the unprocessed scan dataset to be georeferenced. Select that folder.
- 6. Emesent Aura will automatically detect any landmarks in your dataset. Landmarks are distinct and recognizable features in the real world that have been accurately measured and identified during a ground survey.

You can choose to use these identified landmarks or click **Import CSV** then browse for the **.csv** file that contains the survey data you would like to use.

			ADD GCP DA	TA			
	Please add the unprocessed scan dataset you would like to georeference:			CHAN	IGE SCAN DATA		
	Add the survey	d the survey data you would like to use by importing a .csv file:				MPORT CSV	
	ID	Coord X (m)	Coord Y (m)	Coord Z (m)	Radius (m)	Delete	
	GE01_39	200335.874188	200393.289376	-377.761815	0.125	Θ	
	GE02_39	200336.688766	200394.26222	-378.22264	0.125	Θ	
	GE03_39	200337.48207	200395.236179	-377.720257	0.125	Θ	
	GE04_39	200339.780509	200388.888131	-377.887334	0.125	Θ	
	GE05_39	200340.453174	200389.536273	-378.544714	0.125	Θ	
						DELETE ALL	
S Landmarks detected in the selected folder							
						_	
						SAVE	CANC

If you have done GCP processing in this directory before, Emesent Aura will remember your previous landmarks. The software will also check to see if there are any missing fields in your survey data.

• After you have imported your CSV file, the data is not editable from within the software. If you have made a mistake, modify your CSV file and import it again. The data will be replaced.

7. Click Save.

8

8. In the **Location** field, enter the preferred name for the output folder. Emesent Aura will create this folder, which stores all the processed results and data, as a child directory within the raw scan folder.



 Select the processing profile for the Process and GCP workflows.
 Refer to the Processing Profiles section for more information about which profiles to use and how to create a custom profile.

If you are using a custom profile, click **Processing Settings** then on the **GCP** tab, make sure **Wait for GCP Target Manual Review** is toggled on. If not, Emesent Aura will assume that the constellation of detected targets has been successfully matched to the survey points provided. For all in-built profiles, this setting is enabled by default. Refer to the Process Tab section for more information on processing settings.

10. Click Save.


0

You can run the processing automatically end-to-end without interaction, although while you're building familiarity with the process we recommend you visualize and review the target detection and constellation matching results in Emesent's point cloud viewer for confirmation or adjustment. For more information on processing GCPs, refer to our *Ground control points* instruction.

7. Start processing


 Click Start to begin processing. The Configure New Scan Job panel is replaced with the Processing Scan panel and shows a progress bar showing how far along you are in your processing job. In addition to the progress bar, the elapsed time of the processing job is shown to the right.

The directory file path below the progress bar provides a way to identify the dataset source. This is useful if simultaneously processing multiple jobs with the same output folder name. Copying the file path and pasting it on your computer's file explorer allows you to access the completed files without having to wait for the processing job to be completed.



8. Review Aura's constellation matching

During the processing phase, targets are automatically detected in the point cloud. Aura will try to find clusters of points that look like targets and try to align them with the survey points from the uploaded CSV. At roughly halfway through the process, the **Status Bar** turns blue and will prompt you for manual input. You will now need to check the associations between your landmarks and your targets.



1. Click **Load Constellation** to open the intermediate point cloud and the associated constellation file.

Because these two files are associated when you remove one file, the other will also close.

• Emesent Aura is not designed to handle two separate constellations. If you load more than one constellation, there is a possibility that they will not update properly. It is strongly recommended to load one constellation at a time.



8



2. If you have existing scans, you will be prompted to remove them. Save any changes you have made to these existing scans then click **Remove**. This is necessary to prevent issues with global point placement due to differing reference frames.

~~							
REMOVE EXISTING SCANS							
	Would you like to continue with loading the constellation and remove the 4 existing point clouds and/or constellations?						
	Please save any changes you have made to loaded point clouds and/or constellations before continuing.						
i	 This is a necessary step to prevent issues with global point cloud placement due to differing reference frames. 						
_							
	REMOVE		CANCEL				


3. Select the intermediate point cloud to display it with an overlay of the targets. This will allow you to see how well the software has detected targets and automatically aligned them to landmarks. They will not necessarily be completely aligned at this stage (this difference is effectively the drift).

i The **Intensity** color scale helps you see identified targets more easily.

- 4. Go to the **GCPs** section in the **Visualize** tab and click on your constellation file to display the Context panel.
 - **A green box:** Indicates that the target has been associated with a landmark.
 - **A blue box:** Indicates that the targets haven't been associated with a landmark. Review these targets and delete them if you find they are not necessary.



• The associated landmark is shown with a connecting line.



- 5. If there haven't been enough targets detected, change the GCP parameters and go through the process again.
- 6. If there is a visible target that hasn't been detected, use the **Select Points** tool to select the undetected target.
- 7. Go to the **Inactive Targets** menu on the right, then assign the target (if required) using the **Assign** tool. The assignment only works with objects in the point cloud that look like a target with high intensity.

9. Adjust the point cloud

Before you make associations between targets and landmarks, it is a good idea to check that the point cloud is in the correct position. From a target identification and processing perspective, they don't *need* to be closely aligned. But the advantage of doing this is that it will help you understand which target is which.


Sometimes it can be difficult to see which landmark is associated with its corresponding target in the point cloud. To make it easier to determine the correct associations, it can be helpful to move the point cloud so that the targets line up better with the landmarks in the constellation.

If the position of the point cloud needs adjusting:

- 1. Go to the **Visualize** tab.
- 2. In the **Point Clouds** section, click on your point cloud.
- 3. In the Main toolbar, click **Translate** to move the point cloud.

10. Match targets to the correct landmark

This part of the process allows you to make sure that all target associations are correct. This will influence processing once it resumes. Misaligned targets need to be unassigned and then reassigned correctly.




To align a target to the correct landmark:


- 1. Go to the **Visualize** tab.
- 2. In the **GCPs** section, select the correct constellation.
- 3. In the Context panel, go to **Edit Constellation**.

0

In this example, the targets are aligned to the wrong landmarks. The associated landmark is shown with a connecting line. The misaligned targets are highlighted on the right.




4. Drag the target (target_3) to the **Inactive Targets** menu to unassign it. The box will turn blue instead of green.




5. Repeat for any other misaligned targets (in this case, target_5).


Both of the target bounding boxes should now be blue.
 You can delete any inactive targets by selecting the target and then clicking the
 Trash Target icon.



6. Reassign targets by dragging them one at a time back to the correct landmark in the **Edit Constellation** menu. The correct landmark is the one closest to the target.




7. After you have realigned both targets, the bounding boxes should become green again.



11. Save the constellation file

Once you are happy with your target associations, go to the **Edit Constellation** menu and click **Save**.



- 1. **Quick save:** This option is only available when running the GCP workflow in Emesent Aura. The new file will overwrite the *constellation.yaml* file that was originally produced by the processing software.
 - 2. Save Constellation: Opens the Save as dialog box.

Ø

12. Finish processing

1. Click **Confirm** to continue your GCP processing job. This is the point in the GCP processing where the drift in the point cloud will be fixed.

~	DETECTING TARGETS - REVIEW GCP			
	Output-(12) 55% CANCEL REVIEW 00P 00:15:39			
	File path location: C:/Scans/GCP Scan			
	Constellation loaded, please manually reacisign targets within your constellation if required			
	RELOAD CONSTELLATION CONFIRM BACK			

Clicking **Reload Constellation** discards your changes and loads the original constellation.

You will get a notification that says the constellation and the associated point cloud have been removed. This is fine. Emesent Aura removes the point cloud and the constellation from the viewport, as it is no longer needed.

0

13. View the final output

Once processing has finished, you will get a notification that the GCP process is complete. In the processing panel, you will get a breakdown of all the outputs from your processing job. (This panel is a mirror of the output folder structure).

	GCP COMPLETE	
Output-{12} 100%		COMPLETED 00:23:25
File path location: C:/Scans/GCP Scan		
Files		
GCP Scan_laz1_4.laz	474.58 MB	
GCP Scan_subsampled_laz1_4.laz	51.87 MB	
GCP Scan_traj.xyz	15.19 MB	
ground_control_accuracy_analysis.csv	916 Bytes	

- 1. Click **View** beside each generated file to load them into the Viewport for analysis or further editing.
 - a. Full Point Cloud

The point cloud with the complete set of data points. The output file type varies depending on the profile that was used in generating the point cloud. The filename includes the output folder name with the output file type appended to it. For example: *Output_laz1_4.laz* where the output file type is PointCloud LAZ (1.4) and the file is located in the "Output" folder.

b. Subsampled Point Cloud

The point cloud containing a subset of points from the original point cloud dataset. This output is only generated if **Subsample Point Clouds** is enabled in the **Output** tab of the **Processing Settings** panel.

- c. Trajectory File The data file contains the movement or path of the Hovermap as it acquired the point cloud data.
- Ground Control Accuracy Analysis
 A CSV file that provides an assessment of the accuracy achieved during the georeferencing process. It contains information about how well the georeferenced point cloud aligns with the known real-world coordinates of the GCPs.
- 2. Click **Open Folder** to view the output folder.





PREPARED BY: EMESENT PTY LTD LEVEL G, BUILDING 4, KINGS ROW OFFICE PARK 40-52 MCDOUGALL ST, MILTON, QLD, 4064 AUSTRALIA

EMAIL: CUSTOMER-SUCCESS@EMESENT.IO PHONE: +61735489494